



a (





Follow us here to see more exciting projects and ideas!



Fabric Needed

3 Wishes Fabric® Happy Fall Collection

- 7/8 yd Flowers (18120-TAN-CTN-D)
- ½ yd Black Solid
- 3/8 yd Patchwork (18116-MLT-CTN-D)

Additional Supplies Needed:


- 6" x 9" (15.24 cm x 22.86 cm) Lightweight fusible web
- 16 ¾" x 16 ¾" (42.55 cm x 42.55 cm) piece of paper/tissue (for Pattern)
- Chopstick
- Scotch Tape
- Fabric and paper scissors
- · Piecing and sewing thread
- Quilting and sewing supplies

Before You Begin


Read all instructions before beginning project. Do not pre-wash fabrics. Press fabrics with a dry iron on cotton setting before cutting. Use a ¼" (6.35mm) seam allowance and sew fabrics with right sides together (RST) unless otherwise noted. Backstitch at beginning and end of seams.

Cutting

Use a rotary cutter and ruler or scissors to cut the pieces from each fabric listed below. **Note:** Refer to instructions to create Apron Pattern and Pocket Appliqué.



Flowers – 18120-TAN-CTN-D (% yd x wof / 80.01 cm x 106.68 cm) Cut 1 – Apron on fold from pattern



Black Solid – (½ yd x wof / 45.72 cm x 106.68 cm)
Cut 2 – 3" x 41" (7.62 cm x 104.14 cm) for Waist Ties
Cut 1 – 3" x 24" (7.62 cm x 60.96 cm) for Neck Strap


Cut 1 – 3" x 24" (7.62 cm x 60.96 cm) for Neck Strap Cut 2 – 6 ½" x 15 ¾" (16.51 cm x 40.01 cm) for Pocket and Pocket Lining




Patchwork – 18116-MLT-CTN-D (¾ yd x wof / 34.29 cm x 106.68 cm) Fussy Cut 1 – 4 ¾" x 7 ½" (12.07 cm x 20 cm) Pocket Appliqué

Sewing

1. Make an Apron Pattern from the two printed pattern pieces and a 16 ¾" x 16 ¾" (42.55 cm x 42.55 cm) square of paper. Measure 2 ½" (6.35 cm) from the top right edge of the square and make a mark. Draw a line to connect the mark and the lower right corner as shown in Diagram A. Lay out the pattern pieces with the square, overlapping the dotted lines and tape together. Cut out the pattern along the drawn and printed lines.



2. Fold the Flowers fabric **wrong** sides together so selvages meet. Place the Apron Pattern on the fold and cut one Apron 30" x 32 ½" (76.2 cm x 82.55 cm).



3. Place Patchwork fabric with **wrong** side up. Center the adhesive side of the Lightweight fusible web rectangle (6" x 9" / 15.24 cm x 22.86 cm) over the Autumn Truck motif as shown in Diagram C. Fuse according to the manufacturer's directions. Fussy cut a rectangle (4 ³/₄" x 7 ⁷/₈" / 12.07 cm x 20 cm) with the Autumn Truck motif centered. Remove paper backing.



Fuse wrong side




Fussy Cut Autumn Truck

Autumn

4 34" x 7 7/8"

4 ³/₄" x / //₈" (12.07 cm x 20 cm)


4. Fold the Pocket (6 ½" x 15 ¾" / 16.51 cm x 40.01 cm) in half and lightly press a crease in both directions to mark the center. Center the Autumn Truck appliqué (4 ¾" x 7 %" / 12.07 cm x 20 cm) as shown in Diagram D. Fuse according to the manufacturer's directions. Secure the outside edges with a machine buttonhole stitch or small zig-zag stitch (*Tip: Test stitch length and stitch width on fabric scrap*).



5. Place the Pocket Lining (6 ½" x 15 ¾" / 16.51 cm x 40.01 cm) and the Pocket (6 ½" x 15 ¾" / 16.51 cm x 40.01 cm) RST with edges even as shown in Diagram E; pin. Sew around all edges leaving a 3" (7.62 cm) opening in the bottom for turning. Start and stop with a backstitch. Clip corners and turn right side out through opening. Use a chopstick to carefully push out corners; press. Topstitch ¼" (6.35 mm) from the top edge. The Pocket should measure 6" x 15 ¼" (15.24 cm x 38.74 cm).



6. Center Pocket on Apron 4 ½" (11.43 cm) from the bottom edge as shown in Diagram F and pin. Sew around sides and bottom, closing the bottom opening. Sew a vertical line down the center of the appliqué to divide the Pocket into two sections.




7. Fold the Neck Strap (3" x 24" / 7.62 cm x 60.96 cm) RST lengthwise as shown in Diagram G. Pin and sew around the open edges leaving a 3" (7.62 cm) opening to turn. Clip Corners and turn right side out, press. Topstitch around all sides, closing the opening to complete the Neck Strap 1 ¼" x 23 ½" (3.18 cm x 59.69 cm).




8. Fold one Waist Tie (3" x 41" / 7.62 cm x 104.14 cm) RST lengthwise as shown in Diagram H. Pin and sew around one end and long edge leaving the other end open to turn. Clip Corners and turn right side out; press. Topstitch around the sewn end and both sides to complete the Waist Tie 1 1/4" x 40 3/4" (3.18 cm x 103.51 cm). Make two.




9. Press each edge of the Apron 1/4" (6.35 mm) to the **wrong** side.



Press the armholes and bottom edge another ¼" (6.35 mm) to the **wrong** side and topstitch close to the inside fold.



Press the top edge and sides an additional 1" (2.54 cm) to the **wrong** side and topstitch close to the inside fold.



- 10. Attach the Neck Strap as shown in Diagram J. Pin, then try on and adjust length if desired. Secure by sewing a 1" (2.54 cm) square through all layers.
 - 1 Attach unsewn edge of one Apron Tie to the back of the Apron as shown and sew using the hem line as a stitching guide.
 - 2 Fold Apron Tie back over the seam just sewn and sew along the edge of the apron. Repeat to attach the second Apron Tie.


The finished Apron should measure approximately $28 \frac{1}{4}$ " x 30" (71.76 cm x 76.2 cm).



Finished Care Instructions

Machine wash in cold water; gentle cycle. Do not Bleach. Tumble dry low or hang to dry and press if needed.

Apron Pattern – Section 1 (100% Scale)							Scale: 1 square = 1" x 1"	
	Fold Fold		Apron Patte Section	ern I				Overlap Apron Section 2



Overlap Apron Square – 16 ¾" x 16 ¾"